

BCT License Transfer

Please fill out this form and fax (+49 7852 996-100) or email (support@bct-technology.com) back to us for review.

Company Name: _____

First Name: _____

Last Name: _____

Mailing Address: _____

Phone: _____

Fax: _____

Email: _____

Please send us the new BCT software key for the following product:

BCT-SoldTo-ID: _____

Previous LAN-ID/MAC address: _____

New LAN-ID/MAC address: _____

Previous Server Name: _____ (only Floating Licenses)

New Server Name: _____ (only Floating Licenses)

We confirm that the new BCT software key only has been requested for the following reason:

Systems Change (e.g. IBM → Sun, UNIX → Windows)

Previous System: _____ New System: _____

Change of Network Card

Typing errors or other mistakes at previous key transfer

Other reasons (please state in detail) _____

We confirm that the previous key will no longer be used and that the relevant software will only be applied on the new server specified above.

Name

Date, Place

Signature, Company Stamp

Additional Information on BCT License Transfer

Where do I find the certificate number for BCT-Software?

The certificate is written on an extra sheet of paper in the BCT software package. It is also saved in the license file. Just open the file e.g. bctv170.dat (170 = UG V17) with an text editor and look for „VENDOR_STRING=??-????????????“.

Where do I find the license file?

BCT Products need an environment variable „BCT_EOMS_DIR“ that refers to the installation directory. This directory contains a subdirectory called „bct_def“, that contains the startfiles: eoms_set.cmd (Windows) and eoms_export.sh (Unix). The variable „BCT_LICENSE_FILE“ defines the path to the license file.

Wrong NX Version in the license file?

The license file is downward compatible, which means that you can also use the BCT Software with previous NX Versions.

What is the difference between a nodelocked and floating license?

Nodelocked licenses (Cert No. NC-????????????) are only available on one specific CAD workstation. The software is locked to this machine by the LAN-ID of the network card.

Floating licenses (Cert No. FC-????????????) are available on multiple CAD workstations via license server. BCT Software checks if there are free licenses available on the server. The software is locked to the server name and LAN-ID of the network card.

What is a LAN-ID/MAC address?

It is the physical address of the network card and absolute unique. This address is needed to generate your specific license file.

Where can I get the LAN-ID/MAC address?

On Windows NT 4.0 or Windows 2000 open a MS-DOS Shell and enter „ipconfig -all“ [Enter]. You will get :

```
Windows NT IP Configuration
    Host Name : .....: bct_pc114
    ....

Ethernet Adapter AMDPCN1:
    Description .....: AMD PDCNET Family Ethernet Adapter
    Physical Address.....: 00-60-B0-B5-EE-EE
    DCCP activated.....: No
```

Where can I get more technical information?

<http://www.bct-technology.com/en/support-services/license-requests.html>

For direct support please call +49 7852 996-222.